

MORFIN AUTH WINDOWS CSHARP SDK

Version: 1.0.0.0

Supported Devices

MFS500, MELO31, MARC10

Contents

- Contents 1
- CONTROL SHEET 2
- DOCUMENT HISTORY 2
- 1. Overview 2
- 2. Prerequisite 2
- 3. Functions..... 3
 - 3.1. Initialize Device..... 3
 - 3.2. Device Connected Status 4
 - 3.3. Get SDK Version 4
 - 3.4. Start Capture 4
 - 3.5. Start Auto Capture 5
 - 3.6. Stop Capture 5
 - 3.7. Get Capture Finger Image 5
 - 3.8. Get Capture Finger Template 6
 - 3.9. Match Finger Template (1:1)..... 7
 - 3.10. Uninitialized Device..... 7
 - 3.11. Get Error Description 7
 - 3.12. Get Device List 7
 - 3.13. Get Supported Device List..... 8
 - 3.14. Enable Logs..... 9
 - 3.15. Auto Device Detect Event 9

CONTROL SHEET

DOCUMENT TITLE	MORFIN AUTH WINDOWS CSHARP SDK Version : 1.0.0.0
RELEASE DATE	26/06/2023
PROJECT TEAM	Rajesh Koriya, Devyang Sathavara , Henry Roy
PREPARED BY	Rajesh Koriya
REVIEWED BY	Mahesh Patel
APPROVED BY	Mahesh Patel
SECURITY CLASSIFICATION	Restricted

DOCUMENT HISTORY

Document Version	Release Date	Release Notes	Author
1.0.0.0	26/06/2023	Initial release document	Rajesh Koriya

1. Overview

The document provides the functional and implementation information to work with MELO31, MARC10, MFS500 and you can also match finger (1:1) using ISO or ANSI template.

2. Prerequisite

SDK required below dependency.

- Window 10 and above
- .Net Framework 4.8 and above.
- VC redist 2013 & 2015
- Morfin Driver Setup

3. Functions

3.1. Initialize Device

Used for Initialized devices with manufacture data.

CSharp:

```
public int Init(string strProductName, int intProductNameLen, ref FINGER_DEVICE_INFO
StDeviceInf);
```

Structure:

```
public struct MORFin_DEVICE_INFO
{

[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.Un
managedType.ByValTStr, SizeConst = 13)]
    public string SerialNo;

[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.Un
managedType.ByValTStr, SizeConst = 13)]
    public string Firmware;

[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.Un
managedType.ByValTStr, SizeConst = 7)]
    public string Make;

[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.Un
managedType.ByValTStr, SizeConst = 12)]
    public string Model;

    public int Width;

    public int Height;

    public int DPI;

[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.Un
managedType.ByValTStr, SizeConst = 20)]
    public string PCBSerialNo;

}
```

Parameters:

```
string strProductName:
    [in] User passed product name.
int intProductNameLen:
    [in] User passed product name length.
ref FINGER_DEVICE_INFO StDeviceInf:
    [ref] Device initiation success on return device information.
```

Return Values:

```
0   = Success
0!  = Failed
```

3.2. Device Connected Status

Used for checking device connected or not.

CSharp:

```
public int IsConnected(string strProductName);
```

Parameters:

string strProductName:
[in] User passed product name.

Return Value:

0 = Connected
0! = Failed

3.3. Get SDK Version

Return SDK version.

CSharp:

```
public int GetSDKVersion(out string Ver);
```

Parameters:

string Ver:
[out] Return SDK version.

Return Value:

0 = Success
0! = Failed

3.4. Start Capture

Used for asynchronously capture. Device initialization required.

CSharp:

```
public int StartCapture(int Timeout = 10000, int MinimumQuality = 40)
```

Preview Call back:

```
void OnPreview(CaptureData ObjCaptureData);
```

Capture Complete Call back:

```
void OnCaptureCompleted(CaptureData ObjCaptureData);
```

Finger Position Call back :

```
void OnFingerPosition(CaptureData ObjCaptureData);
```

Parameters:

int MinimumQuality:
[in] Quality range 1 to 100.
int Timeout:
[in] Timeout value set in milliseconds. If timeout set 0 then capture will be stops after finger detected with desired quality.

CaptureData ObjCaptureData:

Bitmap AutoCaptureBitmap.
[out] Preview bitmap Image.
int ErrorCode.
[out] Error Code while capturing.
Int Quality;
[out] Image Quality while capturing.
int Nfiq
[out] NFIQ Score after capturing success.

Return Value:

0 = Capture started

0! = Capture start failed

3.5. Start Auto Capture

Used for synchronously capture. Device initialization required.

CSharp:

```
public int AutoCapture(out int Qlt, out int Nfiq, int TimeOut = 10000, int MinimumQuality = 40);
```

Preview Call back:

```
void OnPreview(CaptureData ObjCaptureData);
```

Finger Position Call back :

```
void OnFingerPosition(CaptureData ObjCaptureData);
```

Parameters:

int MinimumQuality:
[in] Quality range 1 to 100.

int Qlt:
[out] Get quality on success.

int Nfiq:
[out] Get Nfiq on success.

CaptureData ObjCaptureData:
Bitmap AutoCaptureBitmap.
[out] preview bitmap Image.

int ErrorCode.
[out] Error Code while capturing.

Int Quality;
[out] Image Quality while capturing.

Return Value:

0 = Capture started
0! = Capture start failed

3.6. Stop Capture

Used for forcefully capture stop while capturing.

CSharp:

```
public int StopCapture();
```

Return Value:

0 = Success
0! = failed

3.7. Get Capture Finger Image

Used for getting finger image like "BMP", "PNG", "JPEG2000", "WSQ", "RAW", "FIR_V2005", "FIR_V2011", "FIR_WSQ_V2005", "FIR_WSQ_V2011", "FIR_JPEG2000_V2005" and "FIR_JPEG2000_V2011". Capture success required.

CSharp:

```
public int GetImage(out byte[] bytesTemplate, IMAGE_FORMAT Format, int CompressionRatio);
```

Enum:

```
public enum IMAGE_FORMAT {
    BMP = 0,
    JPEG2000 = 2, WSQ = 3,
    RAW = 4,
    FIR_V2005 = 5,
    FIR_V2011 = 6,
    FIR_WSQ_V2005 = 7,
    FIR_WSQ_V2011 = 8,
    FIR_JPEG2000_V2005 = 9,
    FIR_JPEG2000_V2011 = 10,
};
```

Parameters:

byte[] bytesTemplate:
[out] Last captured finger print image in bytes.
IMAGE_FORMAT format:
[in] Passed image format.
Int CompressionRatio :
[in]Pass (1-15) range for JPEG2000 and (1-10) for WSQ image.

Return Value:

0 = Success
0! = failed

3.8. Get Capture Finger Template

Used for getting finger print template as per mention enum . Capture success required.

CSharp:

```
public int GetTemplate(out byte[] bytesTemplate, TEMPLATE_FORMAT Format, int
CompressionRatio);
```

Enum:

```
public enum TEMPLATE_FORMAT {
    FMR_V2005 = 0,
    FMR_V2011 = 1,
    ANSI_V378 = 2,
};
```

Parameters:

byte[] bytesTemplate:
[out] Last captured finger template in bytes.
TEMPLATE_FORMAT format:
[in] Passed template format
Int CompressionRatio :
[in]Pass (1-15) range for JPEG2000 and (1-10) for WSQ template.

Return Value:

0 = Success
0 ! = failed

3.9. Match Finger Template (1:1)

Used for matching fingerprint (1:1).

Csharp:

```
public int MatchTemplate(byte[] probTemplate, int probTemplateLen, byte[] galleryTemplate, int galleryTemplateLen, out int MatchScore, TEMPLATE_FORMATFormat);
```

Parameters:

byte[] probTemplate:
[in] Passed probe template
int probTemplateLen:
[in] Passed probe template length
byte[] galleryTemplate:
[in] Passed gallery template
int galleryTemplateLen:
[in] Passed gallery template length
int MatchScore:
[out] Return matching score. (0- 1000 range)
TEMPLATE_FORMAT format:
[in] Passed template format

Note: This Functionality working with FMR_V2005, FMR_V2011 and ANSI_V378 Template only.

Return Value:

0 = Success
0! = failed

3.10. Uninitialized Device

Used for uninitialized device and free all allocated memory.

CSharp:

```
public int Uninit();
```

Return Value:

0 = Success
0! = failed

3.11. Get Error Description

Used for getting description respect to error code.

CSharp:

```
public string GetErrDescription(int err);
```

Parameters:

int err:
[in] Pass Error Code Generated by SDK.

3.12. Get Device List

Used for getting device list on success.

CSharp:

```
public int GetConnectedDevices(DEVICE_LIST[] DeviceList, out int DeviceCnt);
```

Structure:

```
public struct DEVICE_LIST{
```

```
[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.UnmanagedType.ByValTStr, SizeConst = 12)]
```

```
    public string Model;
```

```
}
```

Parameters:

```
    DEVICE_LIST[] DeviceList:
```

```
        [out] Structure with Connected Device List.int
```

```
    DeviceCnt :
```

```
        [out] Connected Device Count.
```

Return Value:

```
    0 = Success
```

```
    0 != failed
```

3.13. [Get Supported Device List](#)

Used for getting supported device list in SDK on success.

CSharp:

```
public int GetSupportedDevices (DEVICE_LIST[] DeviceList, out int DeviceCnt);
```

Structure:

```
public struct DEVICE_LIST
```

```
{
```

```
[System.Runtime.InteropServices.MarshalAsAttribute(System.Runtime.InteropServices.UnmanagedType.ByValTStr, SizeConst = 12)]
```

```
    public string Model;
```

```
}
```

Parameters:

```
    DEVICE_LIST[] DeviceList:
```

```
        [out] Structure with Connected Device List.int
```

```
    DeviceCnt :
```

```
        [out] Connected Device Count.
```

Return Value:

```
    0 = Success
```

```
    0 != failed
```

3.14. Enable Logs

Used for tracing application log

CSharp:

```
public int EnableLogs (MorFin_AUTH_LOG_LEVEL eLogLevel, string pFolderPath);
```

Enum:

```
public enum MorFin_AUTH_LOG_LEVEL
{
    MorFin_AUTH_LOG_LEVEL_OFF = 0,
    MorFin_AUTH_LOG_LEVEL_ERROR = 1
}
```

Parameters:

MorFin_AUTH_LOG_LEVEL eLogLevel:

[in] pass enum log level.

string pFilePath:

[in] Logs will be saved on folder path, if folder path is blank then logs will be saved on application path (default).

Return Value:

0 = Success

0! = failed

3.15. Auto Device Detect Event

Used for device detection call back registration.

CSharp:

```
void OnDeviceDetection(string DeviceName DEVICE_DETECTION_EVENT dvcStatus)
```

Enum:

```
public enum MorFin_AUTH_LOG_LEVEL
{
    EVENT_DISCONNECTED = 0,
    EVENT_CONNECTED = 1
}
```

Parameters:

string DeviceName:

[out] Get device name while device detection.

DEVICE_DETECTION_EVENT dvcStatus:

[out]: Status of the device - Connected/Disconnected from enum.